


PI - FAB

CNC Lab

RhinoCAM Post Issue




Introduction


This short tutorial walkthrough how to load the post processors for RhinoCAM 2019 when they do not load in or drop down menu is blank.

1. Launch Control Panel

Launch the Control Panel for the computer and switch the View from "Category" to "Small/Large Icons"




Double click on File Explorer Options




2. File Explorer Options

Switch to the View tab of the File Explorer Options. Turn on "Show hidden files, folders, and drives." Click Apply.




3. Load Posts in RhinoCAM 2019

Open the Post settings in RhinoCAM 2019. Click the “...” button next to the path location.




4. Set File Path to Post

Go to "Program Data and drop down the arrow




4. Cont.

Go to “MecSoft Corporation and drop down the arrow. Drop down the “RhinoCAM 2019 for Rhino 6.0” arrow.



Select the "MILL" folder and click OK.



5. Set RhinoCAM 2019 Post

All posts pre-loaded in RhinoCAM 2019 will load.
Please set Current Post Processor to Technosel.

